

How to run it

1 - Clone the git repository: <https://github.com/ferolifil/bees-case>

2 - Run Docker. On PowerShell navigate to the root directory where git was cloned:

```
cd \<your_path>\bees-case\
```

3 - Run airflow container with command:

```
docker run -d -p 8080:8080 -v "$PWD/airflow/dags:/opt/airflow/dags/" --entrypoint=/bin/bash  
--name airflow apache/airflow:2.10.1-python3.8 -c '(airflow db init && airflow users create  
--username admin --password beescase --firstname Fernando --lastname Oliveira --role  
Admin --email admin@example.org); airflow webserver & airflow scheduler'
```

Connect to airflow container:

```
docker container exec -it airflow bash
```

Install required libraries:

```
pip install boto3 timedelta
```

4 - Run Min.IO container with command:


```
docker run --name minio -d -p 9000:9000 -p 9001:9001 -v "$PWD/datalake:/data"  
minio/minio server /data --console-address ":9001"
```

5 - Connect to airflow UI and add airflow variables as example

Connect to: <https://localhost:8080>

login: admin

senha: beescase



| Key | Val | Description | Is Encrypted |
|----------------|---|-------------|--------------|
| app_file_name | analytic_file.csv | | False |
| api_url | https://api.openbrewerydb.org/breweries | | False |
| bronze_path | bronze | | False |
| email | ferolifil@gmail.com | | False |
| gold_path | gold | | False |
| minio_login | minioadmin | | False |
| minio_password | ***** | | False |
| minio_server | http://172.17.0.3:9000 | | False |
| raw_file_name | raw_data.json | | False |
| silver_path | silver | | False |


Admin >> Variables


Variables List:

- agg_file_name / analytic_file.csv
- api_url / <https://api.openbrewerydb.org/beereries>
- bronze_path / bronze
- email / <your_email>
- gold_path / gold
- minio_login / minioadmin
- minio_password / minioadmin
- minio_server / <Min.IO server address>
- raw_file_name / raw_data.json
- silver_path / silver

5 - To find Min.IO server address:

Open Docker desktop:





To use Min.IO UI use:

login: minioadmin

password: minioadmin

6 - After finishing the configurations, enable DAGs in Airflow. Following the order:

api_etl >> parquet_etl >> agg_etl

